

# THEMIS

## Data Analysis Software User's Guide

THM-SOC-120  
February 13, 2007

---

Timothy Quinn, THEMIS Science Operations

---

Ken Bromund, THEMIS Science SFW

---

Jim McTiernan, THEMIS Science SFW

---

Dr. John Bonnell, THEMIS EFI

---

Dr. Alain Roux, THEMIS SCM

---

Dr. Uli Auster, THEMIS FGM

---

Dr. Davin Larson, THEMIS SST

---

Dr. Jim McFadden, THEMIS ESA

---

Dr. Harald Frey, THEMIS ASIs

---

Dr. Hannes Schwarzl, THEMIS Science ACS

---

Manfred Bester, THEMIS Mission Operations Manager

---

Vassilis Angelopoulos, THEMIS Principal Investigator



## Document Revision Record


Rev.	Date	Description of Change	Approved By
1	2006-11-13	Draft	-
2	2006-12-11	Refine naming conventions. Reformat, reorganize.	
3	2006-12-20	Document thmsw_0_3b_20061220, incorporate comments received from post-AGU meeting.	
4	2007-02-13	Document for pre-Launch configuration, thmsw_1_0_20070213	

## Distribution List

Name	Email
Jim Lewis, U.C. Berkeley	jwl@ssl.berkeley.edu
Dr. Tai Phan, U.C. Berkeley	phan@ssl.berkeley.edu
Dr. Forrest Mozer, UCB	fmozer@ssl.berkeley.edu
Dr. Robert Ergun, LASP	ree@fast.colorado.edu
Dr. Robert Lin, UCB	rlin@ssl.berkeley.edu
Dr. Chris Cully, LASP	cully@colorado.edu
Dr. Michael Ludlam	mludlam@ssl.berkeley.edu
Dr. Ellen Taylor, U.C. Berkeley	ertaylor@ssl.berkeley.edu
Dr. Krishan Khurana, UCLA	kkhurana@igpp.ucla.edu
Dr. David Sibeck, NASA GSFC	david.g.sibeck@nasa.gov

## TBD List

Identifier	Description
------------	-------------



## Table of Contents

DOCUMENT REVISION RECORD.....	2
DISTRIBUTION LIST.....	2
TBD LIST.....	2
1. INTRODUCTION.....	5
1.1 Purpose and Scope.....	5
1.2 Applicable Documents.....	5
2. BRIEF OVERVIEW OF THE SOFTWARE.....	6
2.1 How to Get Started.....	6
2.2 Availability of Code and Documentation.....	7
2.2.1 Tested Software Releases.....	8
2.2.2 Latest Software Under Development.....	8
2.3 Graphical User Interface.....	8
3. USER'S GUIDE.....	9
3.1 System Requirements.....	9
3.2 Installation and configuration.....	9
3.2.1 IDL PATH setup.....	9
3.2.1.1 IDL PATH Setup on Windows (and IDLDE on UNIX, Linux and Mac).....	9
3.2.1.1.2 IDL PATH Setup for IDL Command Line (UNIX, Linux or Mac OS X).....	10
3.2.1.2 Data Directory Setup.....	10
3.2.2 Loading THEMIS Data.....	11
3.2.2.1 Loading Data With the GUI.....	11
3.2.2.2 Loading Data from the IDL Command Line.....	11
3.2.3 Plot your first plots of ground or space data.....	12
3.2.4 Calibrations .....	12
3.2.5 Coordinate Transformations.....	12
3.3 Managing Your Data Cache.....	13
3.3.1 Configuring Local Data Cache and Remote Access Behavior.....	13
3.3.1.1 Configuration at startup .....	13
3.3.1.2 On-the-Fly configuration.....	14
3.4 General Conventions used in THMSW routines.....	14
3.5 Software Organization.....	14



---

3.6 How to modify code for your own use.....	15
3.7 How to contribute code and modifications.....	16



## 1.Introduction

### 1.1Purpose and Scope.

The THEMIS analysis software is derived from an IDL set of routines that operate on CDFs from existing missions such as Cluster, Wind, Polar and FAST. This software is being re-organized by the THEMIS software developers and scientists, and checked into a software management database—using the freeware Subversion (SVN)—for maintenance, tracking updates and contributions by a distributed team, and ensuring self-compatibility. In addition to the command-line invoked IDL routines, a graphical user interface that prompts the user for opening, analyzing and plotting the THEMIS data is being developed, and is intended to facilitate use of the most useful of the THEMIS routines.

### 1.2Applicable Documents.

- |   |   |
|---|---|
| 1. THM_SYS_012_PDMP                                   | THEMIS Project Data Management Plan     |
| 2. THM_SOC_101_TIME                                   | THEMIS TIME Definition                  |
| 3. THM_SOC_108_GMAG_L1_VARNAMEs                       | THEMIS GMAG Variable Name Def's         |
| 4. THM_SOC_111_SUNSENSPROC                            | THEMIS SUN SENSOR Science               |
| Processing  |   |
| 5. THM_SOC_112_ATTPAIPROC                             | THEMIS Science ATT & Inertia Determ.    |
| 6. THM_SOC_113_FGM_CALPROC                            | THEMIS FGM CAL File and Processing      |
| 7. THM_SOC_114_SCM_CALPROC                            | THEMIS SCM CAL File and Processing      |
| 8. THM_SOC_115_EFI_CALPROC                            | THEMIS EFI CAL File and Processing      |
| 9. THM_SOC_116_ESA_CALPROC                            | THEMIS ESA CAL File and Processing      |
| 10. THM_SOC_117_SST_CALPROC                           | THEMIS SST CAL File and Processing      |
| 11. SAI-SPEC-1079A (Oct 26, 2005)                     | THEMIS Coordinate systems               |
| 12. SAI-RPT-0722a (September, 2006)                   | Probe Alignment Report (MSSS data, p18) |
| 13. pturin e-mail on Faro alignment results (9/28/06) | FGM, SCM mag alignments                 |
| 14. THM-MB-MEC-005-Magnetometer clocking r7.pdf       | MAG clocking angles                     |



## 2. Brief Overview of the Software

The THEMIS Data Analysis Software (hereafter referred to as THMSW) is IDL-based. THMSW routines can be used to download, open, analyze and plot L1 or L2 data and process L1 data into L2 data quantities. There are two main ways to use the programs: with the command line interface, or with the GUI interface.

Future features will include the ability to create L2 data files the L2 data quantities, utility routines to translate data into other products (e.g., ascii) as necessary.

### 2.1 How to Get Started

Assuming you have the software installed, the best place to start is with a crib sheet. The crib sheets in the `idl/themis/examples` folder give end-to-end examples of how to load, process and plot the highest level data available for a given instrument.

Crib sheets in `idl/themis/examples`:

<code>thm_crib_gmag</code>	Crib sheet for GMAG, including wavelet demo.
<code>thm_crib_mom</code>	Crib sheet for particle Moments.
<code>thm_crib_sst</code>	Crib sheet for Solid State Telescope.
<code>thm_crib_fgm</code>	Crib sheet for Flux Gate Magnetometer
<code>thm_crib_scm</code>	Crib sheet for Search Coil Magnetometer – Linux or Windows, only.
<code>thm_crib_efi</code>	Crib sheet for Electric Fields Instrument.
<code>thm_crib_fbk</code>	Crib sheet for Filter Bank.
<code>thm_crib_scm</code>	Crib sheet for Search Coil Magnetometer – Linux or Windows, only.
<code>thm_crib_asl</code>	Crib sheet for loading and displaying All Sky Keogram data.
<code>thm_crib_tplot</code>	Crib sheet for using tplot plotting package, using GMAG data as an example.

You can run any of the crib sheets by typing

```
.run <thm_crib_XXX>
```

when execution stops at a 'stop' command in the crib sheet, type

```
.c
```

to continue.

Alternatively, you can cut and paste from the crib sheet to the command line.

To find more information on any of the THMSW routines used in the crib sheets, use:

- The source code of the crib sheets, which is included in the `idl/themis/examples` directory of the software distribution.
- HTML help included with the software distribution
- IDL XDOC widget. At the IDL prompt, type:  
xdoc
- IDL doc\_library procedure. At the IDL prompt, type:  
doc\_library, 'command\_name'


Sample THEMIS routine documentation:

```
;+
;Procedure: THM_LOAD_GMAG,
```



```
; thm_load_gmag, site = site, datatype = datatype, trange = trange, $
;   level = level, verbose = verbose, $
;   subtract_average = subtract_average, $
;   subtract_median = subtract_median, $
;   varname_out = varname_out, $
;   subtracted_values = subtracted_values, $
;   downloadonly = downloadonly, $
;   valid_names = valid_names
;keywords:
; site = Observatory name, example, thm_load_gmag, site = 'bmls', the
; default is 'all', i.e., load all available stations . This
; can be an array of strings, e.g., ['bmls', 'ccmv'] or a
; single string delimited by spaces, e.g., 'bmls ccmv'
; datatype = The type of data to be loaded, for this case, there is only
; one option, the default value of 'mag', so this is a
; placeholder should there be more than one data type. 'all'
; can be passed in also, to get all variables.
; TRANGE= (Optional) Time range of interest (2 element array), if
; this is not set, the default is to prompt the user. Note
; that if the input time range is not a full day, a full
; day's data is loaded
; level = the level of the data, the default is 'l2', or level-2
; data. A string (e.g., 'l2') or an integer can be used. 'all'
; can be passed in also, to get all levels.
; /VERBOSE : set to output some useful info
; /SUBTRACT_AVERAGE, if set, then the average values are subtracted
; from the loaded variables,
; /SUBTRACT_MEDIAN, if set, then the median values are subtracted
; from the loaded variables,
; varname_out= a string array containing the tplot variable names for
; the loaded data, useful for the following keyword:
; subtracted_values = returns N_elements(varname_out) by 3 array
; containing the average or median (or 0) values
; subtracted from the data.
; /downloadonly, if set, then only download the data, do not load it
; into variables.
; /valid_names, if set, then this will return the valid site, datatype
; and/or level options in named variables, for example,
;
;   thm_load_gmag, site = xxx, /valid_names
;
; will return the array of valid sites in the
; variable xxx
;
;Example:
; thm_load_gmag, site = 'bmls', trange =
; ['2007-01-22/00:00:00','2007-01-24/00:00:00']
;
;Written by: Davin Larson, Dec 2006
; 22-jan-2007, jmm, jmm@ssl.berkeley.edu rewrote argument list, added
; keywords,
; 1-feb-2007, jmm, added subtract_median, subtracted_value keywords
; $LastChangedBy: kenb-mac $
; $LastChangedDate: 2007-02-05 22:58:50 -0500 (Mon, 05 Feb 2007) $
; $LastChangedRevision: 303 $
; $URL:
; svn+ssh://thmsvn@ambrosia.ssl.berkeley.edu/repos/thmsoc/trunk/idl/themis/ground/thm_load_gmag.pro $
;-
```

## 2.2 Availability of Code and Documentation.



### **2.2.1 Tested Software Releases**

Zipped and tested code releases along with corresponding documentation are available in release folders which can be found at the following URL:

<http://themis.ssl.berkeley.edu/socware>

For example, the latest release as of the writing of this document is in:

[http://themis.ssl.berkeley.edu/socware/thmsw\\_1\\_0\\_20070213/](http://themis.ssl.berkeley.edu/socware/thmsw_1_0_20070213/)

Each release folder contains

- idl folder for browsing the source and documentation.
- zip file for download of entire contents of the idl folder.
- doc folder containing the version of this document corresponding to the released software.

The zip file includes IDL files and HTML documentation. HTML-browsable documentation of the IDL routines is available within each release folder at `idl/thmsw_doc.html`.

### **2.2.2 Latest Software Under Development**

The latest THEMIS code being developed and/or integrated at the THEMIS SOC is visible at [http://themis.ssl.berkeley.edu/socware/bleeding\\_edge](http://themis.ssl.berkeley.edu/socware/bleeding_edge). The `idl` subdirectory of `bleeding_edge` is a link to `/disks/socware/idl`, which is the integration/testing area for the latest data analysis software at UCB SSL. There is no guarantee that the software and/or HTML documentation available for browsing is the most up-to-date version available at any given time. The `/disks/socware/idl` workspace can be made up-to-date and a snapshot can be created on demand, to allow access to the latest THEMIS software. The software included in these snapshots is made available without warranty or guarantee. The snapshots will be available as zip files within the `bleeding_edge` folder. Each snapshot zip file contains the complete set of IDL source files and corresponding automatically generated HTML documentation. The snapshot file name corresponds to the SVN revision number and date of the last change that was committed to the THEMIS SVN repository at the time the snapshot was made.

Even more up-to-date and detailed access to the THEMIS code will be available through a web interface to the SVN repository (read-only) `http://` or `svn://` URL to be determined. This is for access to the very latest version of the code, plus possibly access to the SVN change log.

## **2.3 Graphical User Interface**

The philosophy of the graphical user interface GUI is to provide a convenient interface to the most generally useful capabilities of the command-line THEMIS IDL routines. General users can use the GUI without being required to know the individual IDL routines. However, users who want a jump-start to using the more powerful and customizable IDL programming interface may begin with the GUI and then use the GUI to generate a script of the underlying IDL commands which perform the same function. This script can then be used as a starting point for creating an IDL program to process THEMIS data, or can be used as a crib sheet for using the THEMIS IDL programming interface.

The GUI code is bundled together with the THEMIS IDL code distribution, they are downloaded and installed as a single package.

Documentation for the GUI are found within the software distribution at `idl/themis/examples/thm_gui.txt`.

In the future, we hope to make the GUI available as an IDL save file runnable on the IDL Virtual Machine.





## 3. User's Guide

### 3.1 System Requirements

The THEMIS Data Analysis Software requires IDL on Windows or a UNIX-like operating system like Solaris, Linux, or Mac OS X. You must have IDL 6.3 to read the THEMIS CDF data files. Alternatively, you can use an earlier version of IDL, and apply the patch available at [http://cdf.gsfc.nasa.gov/html/idl62\\_or\\_earlier\\_and\\_cdf3\\_problems.html](http://cdf.gsfc.nasa.gov/html/idl62_or_earlier_and_cdf3_problems.html)

Even if you have IDL 6.3, you will want to install the patch if you use IDL to write CDF files. This is because of a bug in IDL 6.3 which will be fixed in 6.4.

Mac OS X notes:

You need X11 to view plots and use the GUI in IDL. You can search for X11 in the Spotlight to see if the X11 application is installed on your system. X11 is available on your Mac installation disks, but may not be installed by default.

There is a known problem, mentioned in the IDL 6.3 release notes, which affects all IDL users running Mac OS 10.4 (Tiger). The `tlimit` command will lock up IDL because the plot window will not receive any mouse clicks.

Workaround: Change the X11 start-up parameters. Do the following:

1. Open any terminal window (in the X11 application menu bar, you can choose `xterm` from the applications menu)
2. Enter the following at the shell prompt:  
`defaults write com.apple.x11 wm_click_through -bool true`
3. Quit X11 (if it is running).

The new default will take effect the next time you start X11, and it will persist from that point (i.e., you will not have to make the change again).

### 3.2 Installation and configuration.

Getting started is usually as simple as downloading the code and setting up your IDL path, according to the instructions, below.

You can download the code from the locations described above in Availability of Code and Documentation.

Once you've downloaded the zip file, choose a location where you want to place the software directory hierarchy.

Unzip the .zip file. It will create a folder with the same name as the zip file. The folder will contain an idl directory.

#### 3.2.1 IDL PATH setup

##### 3.2.1.1 IDL PATH Setup on Windows (and IDLDE on UNIX, Linux and Mac)



For Windows or IDLDE on UNIX, you can use the File->Preferences widget to set up the path so IDL can find the THEMIS IDL files.

UNIX Note: If you use IDLDE on UNIX-like systems, these instructions only work if you do not set the IDL\_PATH environment variable before you call IDLDE. If IDLDE does not allow you to set the path by following these instructions, then follow the instructions for UNIX installation, below.

Start IDL (Windows) or IDLDE (UNIX, Linux, Mac).

Go to File->Preferences  
Select the 'Path' tab.

If <IDL\_DEFAULT> is not present, press 'Insert Standard Libraries'

Press Insert  
Browse to find your installation and select the 'idl/external' directory  
Check the box to indicate "search subdirectories"

Press Insert  
Browse to find your installation and select the 'idl/ssl\_general' directory  
Check the box to indicate "search subdirectories"

Verify that 'idl\_external' is last in the list.

Press Insert  
Browse to find your installation and select the 'idl/themis' directory  
Check the box to indicate "search subdirectories"

### 3.2.1.1.2IDL PATH Setup for IDL Command Line (UNIX, Linux or Mac OS X)

For the command line version of IDL, installation consists of setting up the IDL\_PATH environment variable. The THEMIS Data Analysis Software distribution includes setup scripts, which help set the IDL\_PATH variable correctly.


If you use csh or tcsh, the recommendation is to put the following in your .cshrc  
`setenv IDL_BASE_DIR /path/to/thmsw_v_sb_yyyymmdd/idl`  
`source $IDL_BASE_DIR/themis/setup_themis`

If you use bash shell, the recommendation is to put the following in your .bashrc (Linux) or .bash\_profile (Mac)  
`IDL_BASE_DIR=/path/to/thmsw_v_sb_yyyymmdd/idl`  
`. $IDL_BASE_DIR/themis/setup_themis_bash`

In the above examples, IDL\_BASE\_DIR should be set to the full path name to the idl directory inside the THEMIS Data Analysis Software release.

### 3.2.1.2Data Directory Setup

The THEMIS Data Analysis Software requires a local data directory in which THEMIS data files can be cached. The THEMIS will attempt to create the local data directory for you at the following default location, depending on your operating system.



OS	LOCAL DATA DIR
Windows	C:\data\themis
Solaris, Linux, Mac OS X	~/data/themis

These locations should work as-is for most installations; however, if you don't have administrative privileges to create the data directory in the above locations, you can have your system administrator create it for you, or you can configure the THEMIS Data Analysis Software to use an alternate location. See Remote Data Access and Local Data Cache for information about configuring an alternate location.

### 3.2.2 Loading THEMIS Data

The THEMIS software will automatically create a local data cache which mirrors the structure of the THEMIS data archive. The software is written such that the default settings will work for the majority of users. The location of the THEMIS data archive is also found automatically by the software.

To download some data and load it into IDL, you simply specify a timespan and type of data you want to load. If the data does not exist locally on your local\_data\_dir, it will be downloaded automatically before it is loaded into IDL.

#### 3.2.2.1 Loading Data With the GUI

At the IDL prompt, type  
thm\_gui

Select a timespan, data type, and satellite or ground station. Use the control key to select more than one item the menus. Press the Load button to load the data.

#### 3.2.2.2 Loading Data from the IDL Command Line

At the IDL prompt, type:

```
timespan, '2006-11-11', 1, /day
```

Then, use one of the thm\_load commands, e.g.

```
thm_load_gmag, site='ccnv'
```

Examples of routines for loading data:

thm_load_mom	loads moments data
thm_load_efi	loads efi waveforms
thm_load_fgm	loads all fgm waveforms (choice of fgl, fgh...)
thm_load_scm	loads SCM waveform.
thm_load_gmag	loads ground mag data for any ground station (by keyword) or all available. Keywords to choose high lat and low lat.
thm_load_hsk	loads housekeeping data – all or one by keyword. Important for FGM (temperatures) but also other instruments. Not implemented yet.

Standard Load Procedure Keywords:

SITE	string: ground station name, or a list of ground station names, or 'all'
PROBE	string: probe name, or a list of probe names, or 'all'. e.g. 'a b c'
DATATYPE	type of CDF file for the given instrument.
LEVEL	Level of data file to load: 'l1' or 'l2'
VERSION	Version of CDF file to load (useful for STATE data): 'v01', 'v02'



### 3.2.3 Plot your first plots of ground or space data

In the GUI, press 'Process Data/Tplot'  
You can select the data quantities you want to plot from the 'Loaded Data' list.

In the command line, type  
tplot\_names  
to see available data quantities. Type, e.g.,  
tplot, 1  
to plot the first quantity.

tplot, [1,2,3]  
plots a stack plot of the first 3 data quantities.

Plotting routines:

tplot	General purpose time plotting utility for creating stack plots of waveforms and sonograms.
tlimit	Zoom into or out of a tplot
get_data	Get data out of a tplot variable into a structure containing a time tag array and a data array.
store_data	Store a data array structure into a tplot variable.

Refer to thm\_crib\_tplot for examples of using get\_data and store\_data.

### 3.2.4 Calibrations

Refer to the crib sheet for each instrument for usage of the calibration routines.

Calibration: from L1 data to physical quantities

thm_cal_mom	calibrates all (ESA and SST) moment data
thm_cal_sst	calibrates SST data provides counts, efflux, flux and psd (phase space density or distribution function) data
thm_cal_fit	same as thm_cal_sst, above, but for ESA data.

Beyond calibration: combining physical quantities to create higher level data products: These routines are not implemented yet.

thm_pa_sst	Combines SST psd, and FGM and provides pitch angles dist.
thm_pa_esa	same as above, but combines ESA and FGM.

### 3.2.5 Coordinate Transformations

A coordinate transformation example can be found in thm\_crib\_fgm.pro. The coordinate transformation routines currently work on tplot variables only.

Coordinate transformation routines include:

cotrans	Transform between geophysical coordinate systems
ssl2dsl	Transform between spinning and despun L-vector aligned coordinate system, using data from the STATE file.
dsl2gse	Transform between despun L-vector aligned coordinate system and GSE, using data from the STATE file.



### 3.3 Managing Your Data Cache

There currently exist some experimental routines for managing your THEMIS data file cache. These routines serve as an example of how you will be able to download all data for a given time range with a single command.

- `thm_file_download` – can be used to download all types of THEMIS data for a given time span.
- `thm_file_cleanup` – delete empty directories. This is a function call. It searches the hierarchy and return files matching a given pattern, sorted by access time. Currently does not delete files, but can be used as a tool for finding old data.

#### 3.3.1 Configuring Local Data Cache and Remote Access Behavior

Data locations may be configured at IDL startup (for example, if you want the data to reside in a non-standard location), or dynamically during an IDL session.

The following table summarizes the controls that can be used, in order of precedence:

- `!THEMIS` system variable
- environment variable settings
- `thm_config.pro`

The following table summarizes the settings available:

!themis structure element	Environment Variable	Description
<code>local_data_dir</code>	<code>THEMIS_DATA_DIR</code>	a writable, local directory in which to cache data files
<code>remote_data_dir</code>	<code>THEMIS_REMOTE_DATA_DIR</code>	URL to a data archive where THEMIS data can be found. By default, <a href="http://sprg.ssl.berkeley.edu/data/themis">http://sprg.ssl.berkeley.edu/data/themis</a>
<code>no_download</code>	N/A	1: don't access remote data dir
<code>no_update</code>	N/A	0: download only if file on server differs or if local file does not exist. 1: download only if local file does not exist. i.e. no clobber.
<code>progress</code>	N/A	0: don't show progress bar 1: show progress bar for each file downloaded.
<code>verbose</code>	N/A	level of verbosity for themis commands, 0=silent. Values >1 are generally for debugging.

##### 3.3.1.1 Configuration at startup

For initial configuration, you can set the environment variables specified in the above table. Depending on your operating system and/or shell, this can be done in `.bashrc`, `.cshrc`, or 'System Properties' Window. Alternatively, the `thm_config.pro` file provides a platform-independent and more flexible way of configuring your initial configuration.

1. Make a copy of the `idl/themis/common/thm_config.pro` in a directory outside the THEMIS Data Analysis Software distribution (or edit it in place, if you don't mind losing your changes when you update your software)
2. Add the directory which contains your copy of `thm_config.pro` to your IDL PATH, making sure that it is *before* the `idl/themis` directory. (See IDL PATH setup, above).



3. Edit your thm\_config file to set the environment variables to your liking. See the above table for the names of relevant environment variables.

### **3.3.1.2 On-the-Fly configuration**

The local data directory location can be changed on-the-fly by setting the !themis.local\_data\_dir system variable. For example, when you are connected to the network, you may choose to use a networked data dir:

```
!themis.local_data_dir = '\\justice\data\themis\'
```

The remote\_data\_dir structure element can also be updated to a different URL.

If you want the software to use only locally available data, and don't want the software to try to download data, you can set:

```
!themis.no_download = 1
```

Note that you can only set the !themis variable in an IDL session after a thm\_ command has already been run, or after explicitly calling thm\_init.

## **3.4 General Conventions used in THMSW routines**

The naming convention is that all THEMIS-specific routines begin with thm\_ followed by the function (action) followed by the type of data operated upon. E.g., thm\_load\_xxx reads xxx data.

Non THEMIS-specific routines have a generic name, such as cotrans.

Some routines operate on (as input and/or output) arrays (or structures of arrays returned by get\_data). Others operate on tplot variables (i.e. handles to structures which contain data as well as information about how to display that data in time plots), while in the future we may upgrade the routines to give an option to do either one.

## **3.5 Software Organization**

The themis directory contains THEMIS-specific routines. The general directory (currently named ssl\_general) contains routines which are useful for more than one space-science mission for which THEMIS team members are developing code. The external directory contains packages developed and maintained by other groups, but which are required for writing (and running) the themis and/or general routines.

The idl directory of the distribution includes the following files and sub-directories.



thmsw doc.html	Documentation in HTML format, including alphabetical list of all routines.		
themis/	setup themis	Sample setup script for csh (UNIX)	
	ground/	routines for loading, processing and plotting ground-based data. e.g. thm_load_gmag, thm_gmag_stackplot, imageplot, mosaicplot	
	spacecraft/	fields/	routines for loading, processing and plotting particles data, e.g. thm_proc_fgm
		sst/	(Should be particles/) routines for loading, processing and plotting particles data, e.g. thm_load_sst, thm_cal_sst
	state/	Routines for reading state and performing coordinate transformations, e.g. thm_load_state, cotrans, ssl2dsl, dsl2gse.	
	examples/	Crib sheets, like thm_crib_ask	
ssl_general/	common/	THEMIS-specific tools useful to multiple data types and instruments, eg thm_gui, thm_file_download, thm_init	
	CDF/	CDF utilities, including cdf2tplot, and other utilites like cdf2tplot, cdf_info, cdf_load_vars (into IDL structure representation of CDF)	
	science/	Routines useful for specific scientific analysis.	
	cotrans/	Coordinate transformations: Vectorized version of ROCOTLIB.	
	tplot/	General time-plotting utilites	
	misc/	Miscellaneous routines used by tplot and other ssl_general routines.	
external/	key_param/	Load routines for ACE, KP, WIND, POLAR data.	
	SSW_gen_idl	direct import of a portion of SSW general IDL routines	
	CDAWeb		

The \_themis\_doc.html file contains a complete listing of all routines in the hierarchy, along with links to complete documentation.

### 3.6 How to modify code for your own use

This section gives ideas about you can move beyond the generic capability provided by the GUI and crib sheets.


For command line-based analysis the process of creating new capability would be

1. Modify code generated with the thm\_gui 'History' feature.
2. Modify existing analysis crib sheets
3. Write your own analysis module – an IDL routine - that operates on data
4. Transfer between data arrays and tplot variables
5. Plot the data

You can build on the basic functions of the GUI by:

1. Stringing multiple operations on a pipeline
2. Creating a new operation and corresponding GUI in your local toolkit (not yet implemented).
3. Save a pipeline into a crib sheet (transfer to command line based analysis)
  - a. Use the History and 'Clear History' buttons





---

### ***3.7 How to contribute code and modifications***

If you want to contribute code to the THEMIS IDL SW distribution, you can email us your routines, or you can become part of the THEMIS development team and work directly with the SVN repository. We can give you access if you provide us with your SSH public key. See the THEMIS SOC SW document for details on working with the THEMIS SVN repository.